Wilson[®] Total WipeOut[®] Max Grass & Weed Killer Ready To Use Battery Powered

NON-SELECTIVE HERBICIDE FOR BRUSH, GRASS & BROADLEAF WEEDS

KILLS ROOTS

TREATS (20 m^2) NO RESIDUAL ACTIVITY IN SOIL

NO PUMPING · NO PULLING AA Batteries Included!

DOMESTIC

REG. NO. 29580 P.C.P. ACT

GUARANTEE: Glyphosate 7 g/L (present as isopropylamine salt) Contains 1,2-benzisothiazolin-3-one at 0.038% as a preservative.

READ THE LABEL BEFORE USING KEEP OUT OF REACH OF CHILDREN

[1L - 4L]

Sure-Gro IP Inc./ Lic. Premier Tech Home & Garden Inc. P.O. Box 21001, Brantford, ON N3R 7W9 1-800-268-2806 **DIRECTIONS:** This product is a non-selective herbicide. It controls most annual and perennial grasses, including lawn grasses and quackgrass, broadleaf weeds, such as chickweed, ragweed, knotweed, poison ivy, Canada thistle, milkweed, bindweed and brush, (i.e. virtually anything that is green and growing). It is absorbed by the leaves and moves throughout stem and roots to control the entire plant. Mature perennial weeds should be treated after seed heads, flowers or fruit appear. All plants are most easily controlled in the young, actively growing, seedling stage.

This product wilts and browns plants within 48 hours. Plants usually dry up within 7 to 14 days. There is no soil activity and no run off to affect nearby vegetation. To ensure that this product gets down to the roots, avoid tillage or disturbing the treated area for 7 - 10 days after treatment or as directed below. Make sure to contact only those plants that you want to kill as the spray will damage or kill any desirable plants it contacts. Do not spray in windy conditions. Heavy rainfall immediately after application may wash the chemical off the foliage and repeat treatment may be required. Do not apply if rainfall is forecast. Use a repeat application on any seedlings that re-grow from seeds. Glyphosate is not to be applied using hand-wicking or hand-daubing methods.

HOW TO USE: This product is ready to use. Ensure uniform and complete spray coverage, but not to the point of runoff. 1 L treats 20 m² (5 x 4 paces).

Undesirable vegetation control around buildings, lawn trimming/edging, patio weed control, vacant lots, storage & recreational areas, driveways, hard to mow areas and other similar areas: Apply to vigorously growing plants. Apply to annual weeds anytime after emergence. For perennial weeds apply after seed heads, flowers or berries appear.

Weed control around trees/shrubs/Ornamentals: Apply around base in a neat fashion. Avoid spray or drift contact with foliage, stems or green bark of desirable plants.

Lawn/garden renovation: For best results on lawns, skip one mowing prior to treatment. Allow at least 3 days after treatment before disturbing the soil and/or replanting.

Brush control: Apply after leaves are fully expanded. Treat trees and brush up to 1.5 m in height only; for taller trees and brush, cut back to 1.5 m or cut down and spray re-growth. Controls most brush such as poplar, alder, maple and raspberry.

DIRECTIONS FOR USE OF TRIGGER SPRAYER: EASY SET UP

- 1. Remove sprayer from holder. Gently pull tubing.
- 2. Remove seal from top of cap. Remove plug from cap.
- 3. Securely snap the plug on end of tubing into hole on cap.
- 4. Remove plastic tab to activate batteries.
- 5. Twist nozzle to adjust spray from CLOSE to SPRAY or STREAM.

HOW TO USE

A. Aim toward target weeds and away from people and pets.

B. Press the trigger to spray.

C. Release the trigger to stop spray.

After use: 1. Twist nozzle completely to CLOSE position. 2. Secure sprayer upright in holder.

3. Failure to adjust nozzle completely to CLOSE position and properly secure sprayer in holder may result in leakage and damage to property or injury to people or animals.

(DIRECTIONS CONTINUED UNDER FLAP) Peel back for instructions. Press to reseal.

To replace batteries: 1. Slide battery compartment door to unlatch and open. 2. Remove used batteries and insert new AA batteries *in correct positions* as marked per diagram inside of battery compartment. Never insert the positive end where the negative end belongs and vice versa. Always use a complete set of new batteries of the same type when replacing batteries. *Never* mix alkaline, carbon-zinc or rechargeable batteries. 3. Securely close battery compartment door. 4. *Always* follow manufacturer's recommendations for use and disposal of batteries.

Additional Operating Notes: •Do not submerge in water. •Before each use, inspect sprayer carefully. Make sure hose is flexible and not kinked, worn or cracked, and that all connections are tight. •When storing sprayer for prolonged periods remove batteries. NOTE: Trigger sprayer is to be used only for this product. REMEMBER TO ALWAYS STORE PESTICIDES, CAPS, SPRAYERS AND RELATED EQUIPMENT OUT OF REACH OF CHILDREN AND PETS.

PRECAUTIONS: KEEP OUT OF REACH OF CHILDREN. CAUSES EYE IRRITATION. HARMFUL IF SWALLOWED. Avoid contact with eyes or prolonged contact with skin. Do not allow others such as children and pets on treated areas during application or to re-enter treated areas until spray has dried. Wash immediately after using this product.

FIRST AID: If swallowed, call a poison control centre or doctor immediately for treatment advice. Have person sip a glass of water if able to swallow. Do not induce vomiting unless told to do so by a poison control centre or doctor. Do not give anything by mouth to an unconscious person. If in eyes, hold eye open and rinse slowly and gently with water for 15–20 minutes. Remove contact lenses, if present, after the first 5 minutes, then continue rinsing eye. Call a poison control centre or doctor for treatment advice. If on skin or clothing, take off contaminated clothing. Rinse skin immediately with plenty of water for 15–20 minutes. Call a poison control centre or doctor for treatment advice. Take container, label or product name and Pest Control Product Registration Number with you when seeking medical attention. Take container, label or product name and Pest Control Product Registration.

TOXICOLOGICAL INFORMATION: Treat symptomatically.

STORAGE: Keep product in original container. Store in a cool, dry place away from food, seed and feed.

DISPOSAL: Do not reuse empty container. Remove batteries and dispose accordingly. Wrap container and discard in household garbage.

For additional product information or in case of emergency, spills or fire call toll-free 1-800-268-2806. www.pthomeandgarden.com